# **Protocole MS300 Pocket Pro**

# Spécifications de communication

Baud rate: 38400bps Data: 8 bits

Parity: None
Stopbit: 1 bit
Flow control: None

# 1 Protocole détaillé

# 1.1 Description des messages

# Acknolwedge of a received command (AK):

```
<S>AK_X<E>
X = 'C' accepted, 'F' rejected, 'R' not supported
```

# **Download start marker (DS):**

# **Download end marker (DE):**

```
<S>DE_RR<E>
R = Run number (always 01)
```

### Run, Added Run, Intermediate and Differential Result (RR, GR, IR, DR):

```
<S>RR_ZZZZ_NNNN____HH:MM:SS.FFFFF<E>
<S>IR_I__NNNN____HH:MM:SS.FFFFF<E>
Z = Rank
N = Candidate number (1 - 9999)
I = Inter number
H = Hours (0 - 23)
M = Minutes (0 - 59)
S = Seconds (0 - 59)
F = decimal part (0 - 99999)
System Event (&S):
```

```
<S>&S_EAABBCCDDEEFFGGHH<E>
E = Event ID
A = 1st parameter (Hex format)
B = 2nd parameter if required (Hex format)
H = 8th parameter if required (Hex format)
  E = 0 \rightarrow Buttons(A = Activated key)
                        Bit0 = SPLIT button
                        Bit1 = MEMORY button
                        Bit2 = MODE button
                        Bit3 = START button
       1 -> Buzzer (A = Frequency, B = Beep time in 10ms)
                        Frequency [Hz] = 125000 / A (Ex: "FA" = 500Hz)
Example:
Button START is pressed:
                                                       "&S 008\r\n"
Button START is released:
                                                       "&S 000\r\n"
Button SPLIT and MEMORY are pressed:
                                                       "&S 003\r\n"
Button SPLIT is released, MEMORY still pressed:
                                                       "&S 002\r\n"
Buzzer is turn on at 500Hz during 500ms:
                                                      "&S 1FA32\r\n"
Buzzer is turn on at 1000Hz during 1s:
                                                      "&S 17D64\r\n"
```

# Device specific Event (&E):

```
For HL940:
   <S>&E_MXX<E>
   M = MS300 active mode
    0 = Stopwatch mode
    1 = Time mode
    2 = Countdown mode
    3 = Jumping A mode
    4 = Jumping B mode
    5 = Date mode
    6 = Configure date
    7 = Configure time
    8 = Configure Countdown
    9 = Calibration mode
   X = MS300 program event register (Hex format)
    BIT0 = Mode is changed
    BIT1 = the race is started
    BIT2 = the race is splited
    BIT3 = The countdown is finished
    BIT4 = The intermediate time is finished (mode JMP B)
    BIT5 = The race is paused
    BIT6 = The race or countdown is restart
    BIT7 = The race is stopped
Example:
Stopwatch race is started:
                                                 "&E 002\r\n"
Countdown is paused:
                                                 "&E 220\r\n"
Timing mode is changed to "Date" mode:
                                                 "&E 501\r\n"
Special case:
Countdown finished and restarts automatically:
                                                 "&E 248\r\n"
Jumping A is restarted after a pause:
                                                 "&E 360\r\n"
Jumping B is restarted after a pause:
                                                 "&E 460\r\n"
Jumping A Run is canceled:
                                                 "&E 3C0\r\n"
Jumping B Run is canceled:
                                                 "&E 4C0\r\n"
MS300 is reset (clear all memory):
                                                 "&E 041\r\n"
```

# <u>Serial number + Device type + soft version request (SN):</u>

```
<S>#SN<E>
<S>SN_NNNNN_TTTTTT_VVVV<E>

N = Serial number (0 - 65535)
T = Device type (MS300)
V = Software version (example: VA05)
```

# Synchro time request (#!T):

```
<S>#!T<E>
<S>!T_HH:MM:SS_DD/XX/YY<E>

H = Hours (0 - 23)

M = Minutes (0 - 59)

S = Seconds (0 - 59)

D = Day

X = Month
Y = Year
```

# Serial number programming (#MC): !!! For factory use only !!!

```
<S>\#MC_04660_XXXXXX<E>
X = Serial number (0 - 65535)
```

#### Read a parameters (#RP):

```
<S>#RP_III...<E>
I = parameter ID (000 - 999)
... = See the parameters list on chapter 3.2.
```

# Write a parameters (#WP):

```
<S>#WP_III...<E>
I = parameter ID (000 - 999)
... = See the parameters list on chapter 3.3.
```

# 1.2 Lectures de paramètres

```
002: Timing mode
```

```
#RP_002
    &P_002_XX

XX = Timing mode (HEX format)

For MS300:
    00 = Stopwatch mode
    01 = Time mode
    02 = Countdown mode
    03 = Jumping A mode
    04 = Jumping B mode
    05 = Not used.
    06 = Date mode
    07 = Configure date
    08 = Configure time
    09 = Configure Countdown
    0A = Calibration mode
```

# 025 : Power supply status

```
#RP_025
&P_025_XX_YYY_ZZZ

X = Status register (Hex format)
Y = Battery voltage (0.1V step)
Z = Battery level in % (0-100)

For MS300:
    00 = Battery Full (more than 25%)
    01 = Battery Low (10% - 25%)
    02 = Battery Empty (less than 10%)
    03 = Battery in charge
    04 = Battery fully charged
```

#### Note:

These case cannot append as when the USB is connected, the charge is always active or done. Could be used in future if a radio will be developed.

```
026 : Next candidate number
  #RP_026
   &P_026_XX_YYYY
  X = Input Number (always 00)
  Y = Candidate number (0000 - 0800)
038 : Memory Free
  #RP_038
   &P_038 XXXXX
  X = Memory free value
039 :Run status
  #RP_039
   &P_039 XX
  XX = Status of the RUN (Hex format)
For MS300:
      00 = No race started
      01 = Race started (Only in mode Stopwatch, Time & CountDown)
      02 = Race paused (Only in mode Stopwatch & CountDown)
      03 = CountDown finished, race stopped.
      04 = Jumping CountDown (Only in mode Jumping A & B)
      05 = Jumping Race started
      06 = Second section of Jumping B
      07 = Jumping CountDown paused
      08 = Jumping Race (first section) Paused
      09 = Second section of Jumping B Paused
      0A = Jumping race Finished
      OB = New candidate ready to start (only in mode Jumping A & B)
103: Count Down
  #RP_103
   \& P\_103\_XX\_YYYY
  X = Program number (always 00)
  Y = Count Down value (0000-3599 [sec])
```

# 1.3 Ecriture de paramètres

103: Count Down #WP\_103\_XX\_YYYY

```
X = Program number (always 00)
Y = Count Down value (0000-3599 [sec])
Example:
```

Set the Count Down at 1min30:

"#WP 103 00 0090\r\n"

# 1.4 Liste des commandes

# <u>003 : Open a timing Mode</u> #WC\_003\_XX

```
X = Timing Mode (00-06)
00 = Stopwatch mode
01 = Time mode
02 = Countdown mode
03 = Jumping A
04 = Jumping B
05 = Jumping C (Not used)
06 = Date mode
```

#### 005 : Clear Memory

#WC\_005\_XXXXX

X = Security code (12345)

#### 007 : Start a new synchro

```
#WC_007_TT_HH:MM_DD/XX/YY

T = Synchro Type.
    00 -> Not valid
    01 -> Internal Synchro (take the internal RTC time for synchro)
    02 -> Manual Synchro
    03 -> Not Valid
    04 -> Not Valid
    05 -> Not Valid
    06 -> Configure the internal RTC time (change automatically the mode to "Configure Time" mode, and wait a manual synchro (button or input))

If Manual Synchro is chosen:
```

```
If Manual Synchro is chosen:
```

H = Hour
M = Minute
D = Day
X = Month
Y = Year

### Example:

Take the internal RTC time for a new synchro: "#WC 007  $1\r\n''$  Configure the internal RTC time: "#WC 007 6 16:27  $28/01/13\r\n''$ 

# 008: Trigger a manual input pulse

```
#WC_008
```

Simulate an impulse on the MS300 input.

Turn on the Buzzer at 500Hz during 250ms:

# 009: System cmd

```
#WC_009_XYYZZ
X = Cmd Id
Y = First parameter (Hex format)
Y = Second parameter if required (Hex format)
For HL940 & HL440:
 X = 0 \rightarrow Button
    Y = Button activated (HEX Format
          01 = SPLIT Button
          02 = MEMORY Button
          04 = MODE Button
          08 = START Button
     1 -> Buzzer
                   (Y = Frequency, Z = Beep time in 10ms)
                      Frequency [Hz] = 125000 / A (Ex: "FA" = 500Hz)
Example:
                                               "#WC 009 001\r\n"
Activate the SPLIT Button:
                                               "#WC 009 002\r\n"
Activate the MEMORY Button:
                                               "#WC 009 004\r\n"
Activate the MODE Button:
                                               "#WC 009 008\r\n"
Activate the START Button:
                                               "#WC 009 000\r\n"
Disable all the button:
```

"#WC 009 1FA19\r\n"

#### 012 : Download all the time in memory

```
#WC_012
Example:
#WC 012
DS 01 012 STOPWATCH
RR 0000 0001 00:00:00.98999
RR 0000 0002
               00:00:01.28750
RR 0000 0003
               00:00:01.53280
RR 0000 0004
               00:00:01.77548
RR 0000 0005
               00:00:02.01196
RR 0000 0006
               00:00:02.20843
RR 0000 0007
               00:00:02.46044
RR 0000 0008
               00:00:02.69540
RR 0000 0009
               00:00:02.90020
RR 0000 0010
               00:00:03.19195
RR 0000 0011
               00:00:03.61431
RR 0000 0012
               00:00:03.88693
RR 0002 9999
               00:00:28.35296
DE 01
#WC 012
DS 01 012 JUMPING B
IR 1
        0001
             00:00:01.39877
RR 0000 0001
               00:00:03.03781
        0002
               00:00:00.95498
IR 1
RR 0000 0002
               00:00:03.30108
IR 1
        0003
               00:00:01.39743
RR 0000 0003
               00:00:02.85546
IR 1
        0004
               00:00:01.66546
RR 0000 0004
               00:00:03.43017
IR 1
       0005
               00:00:01.18322
RR 0000 0005
               00:00:13.85415
IR 1
       0006
               00:00:01.38339
RR 0000 0006
               00:00:04.09866
RR 000B 9999
               00:00:04.09866
DE 01
```

Note: The last time is the stopped time (when the run is in Pause) or the running time (Race active). The Rank number is used to indicate the RUN Status (same value as command #RP 039). The candidate number is always set at 9999 to distinguish it.

# 016 : Activation/Deactivation of events messages

#WC\_016\_XX

X = Activation register (hex format)
 X = 0 -> All events are deactivated
 Bit\_0 -> Not valid
 Bit\_1 -> Not valid
 Bit\_2 -> Activate System events '&S'
 Bit\_3 -> Activate Device specific events '&E'
 Bit\_4 -> Activate Timing events 'RR'

All events are disable as soon as the USB in unplugged.

# Example:

Enable system events (Buzzer and Button): "#WC 016 04\r\n" Enable Device specific events: "#WC 016 08\r\n" Enable all events: "#WC 016 1C\r\n" Disable all events: "#WC 016 00\r\n"